

How to upgrade Scena 5m via USB?

Make sure that you have all needed stuff

- USB mass storage device (e.g. USB stick)
- Software Update file (xxx.BIN)

1. As the first step copy the update file to the mass storage device. The file has to be stored in the root folder of the device and make sure that there is only one file in this folder.
2. Switch off the box with the main switch on the back.
3. Now switch the box on, hold and press the up-button on the front panel until the display shows "On The Usb".
4. Connect now the USB mass storage device. The box will do all the next steps automatically.
5. Wait until the box reboots.

Note: Do not switch off your product while it is downloading the software from the USB stick.

Note: In some occasions, a new software may require a factory reset of the product due to the new functionalities it may add.